

Two factor authentication for SonicWALL SRA Secure Remote Access


logintc.com/docs/connectors/sonicwall-sra.html

The LoginTC RADIUS Connector is a complete two-factor authentication virtual machine packaged to run within your corporate network. The LoginTC RADIUS Connector enables SonicWALL SRA remote access appliances to use LoginTC for the most secure two-factor authentication.

User Experience

After entering the username and password into their VPN client, the user is presented with an Authentication Message. The user may enter '1' to receive a push notification to their device to approve or enter a valid One-Time Password (OTP). This flow works the same for clientless access.

Architecture



Compatibility

SonicWALL SRA appliance compatibility:

- SonicWALL SRA Series
- SonicWALL SMA Series
- SonicWALL TZ Series

Appliance not listed?

We probably support it. [Contact us](#) if you have any questions.

Compatibility Guide

SonicWALL SRA and any other appliance which have configurable RADIUS authentication are supported.


Prerequisites

Before proceeding, please ensure you have the following:

RADIUS Domain Creation

If you have already created a LoginTC domain for your LoginTC RADIUS Connector, then you may skip this section and proceed to [Installation](#).

1. [Log in](#) to LoginTC Admin
2. Click **Domains**:
3. Click **Add Domain**:



4. Enter domain information:

Example Inc.

Docs
Support
administrator@example.com

GENERAL
Dashboard
Domains
Users
Logs
SETUP
Administrators
Settings

Domains / Create Domain

Cancel

Name

The domain name will appear on authentication requests (e.g. Office VPN)

Icon

Default
Custom

Connector

RADIUS
API
OpenAM
SiteMinder
Drupal
WordPress
Joomla

RADIUS

Use the RADIUS Connector for your RADIUS appliance

Key Policy

PIN
Passcode

Specify how your users will unlock their token to authenticate

Note: if you are already using passwords for the first factor, we recommend PIN

Create

Name

Choose a name to identify your LoginTC domain to you and your users

Connector

RADIUS

Installation

The LoginTC RADIUS Connector runs CentOS 6.8 with SELinux. A firewall runs with the following open ports:

Port	Protocol	Purpose
22	TCP	SSH access
1812	UDP	RADIUS authentication
1813	UDP	RADIUS accounting
8888	TCP	Web interface
443	TCP	Web interface
80	TCP	Web interface
80	TCP	Package updates (outgoing)

Port	Protocol	Purpose
123	UDP	NTP, Clock synchronization (outgoing)

Note: Username and Password

`logintc-user` is used for SSH and web access. The default password is `logintcradius`. You will be asked to change the default password on first boot of the appliance and will not be able to access the **web interface** unless it is change.

The `logintc-user` has `sudo` privileges.

Configuration

Configuration describes how the appliance will authenticate your RADIUS-speaking device with an optional first factor and LoginTC as a second factor. Each configuration has **4 Sections**:

1. LoginTC

This section describes how the appliance itself authenticates against LoginTC Admin with your LoginTC organization and domain. Only users that are part of your organization and added to the domain configured will be able to authenticate.

2. First Factor

This section describes how the appliance will conduct an optional first factor. Either against an existing LDAP, Active Directory or RADIUS server. If no first factor is selected, then only LoginTC will be used for authentication (since there are 4-digit PIN and Passcode options that unlock the tokens to access your domains, LoginTC-only authentication this still provides two-factor authentication).

3. Passthrough

This section describes whether the appliance will perform a LoginTC challenge for an authenticating user. The default is to challenge all users. However with either a static list or Active Directory / LDAP Group you can control whom gets challenged to facilitate seamless testing and rollout.

4. Client and Encryption

This section describes which RADIUS-speaking device will be connecting to the appliance and whether to encrypt API Key, password and secret parameters.

Data Encryption


It is strongly recommended to enable encryption of all sensitive fields for both PCI compliance and as a general best practice.

The **web interface** makes setting up a configuration simple and straightforward. Each section has a **Test** feature, which validates each input value and reports all potential errors. Section specific validation simplifies troubleshooting and gets your infrastructure protected correctly faster.

First Configuration


Close the console and navigate to your appliance **web interface** URL. Use username `logintc-user` and the password you set upon initial launch of the appliance. You will now configure the LoginTC RADIUS Connector.

Create a new configuration file by clicking **+ Create your first configuration**:



LoginTC Settings

Configure which LoginTC organization and domain to use:



Configuration values:

Property	Explanation
API Key	The 64-character organization API key
Domain ID	The 40-character domain ID
Request Timeout	Number of seconds that the RADIUS connector will wait for

The API key is found on the LoginTC Admin [Settings](#) page. The Domain ID is found on your domain settings page.

Request Timeout

Make a note of what you set the Request Timeout to as you will need to use a larger timeout value in your SonicWALL SRA. We recommend setting the Request Timeout value to 60 seconds in the LoginTC RADIUS Connector and setting the RADIUS authentication server timeout to 70 seconds in SonicWALL SRA.

Click **Test** to validate the values and then click **Next**:

The screenshot shows the 'New Configuration / LoginTC Settings' page in the LoginTC RADIUS Connector 2.1.0 interface. The page is divided into a left sidebar with 'GENERAL' and 'APPLIANCE' sections, and a main content area. The 'GENERAL' section is active, showing 'Configurations' and 'Logs' options. The 'APPLIANCE' section shows 'Status', 'Settings', and 'Upgrade' options. The main content area is titled 'New Configuration / LoginTC Settings' and includes a 'Step 1 of 4' indicator and a 'Cancel' button. Below the title, there is a 'LoginTC Settings' section with a description: 'Values which will dictate how the LoginTC RADIUS Connector will identify itself to the LoginTC cloud service.' This section contains two input fields: 'API Key' with the value 'vZkDw7l6Z3tApwZjXERseKdR0s5RNNqjMxXIwvxpWwjOa9ojXi9b5tdvPyFsqzwj' and 'Domain ID' with the value '9120580e94f134cb7c9f27cd1e43dbc82980e152'. Below these fields, there is a note for each: 'The 64-character organization API key is found on the [LoginTC Admin Panel Settings](#) page.' and 'The 40-character domain ID is found on the [LoginTC Admin Panel](#) domain settings page.' At the bottom of the main content area, there is a 'Test' button and a 'Next' button. A green message bar at the very bottom states 'Test successful, click Next to continue'.

First Authentication Factor

Configure the first authentication factor to be used in conjunction with LoginTC. You may use Active Directory / LDAP or an existing RADIUS server. You may also opt not to use a first factor, in which case LoginTC will be the only authentication factor.

LoginTC RADIUS Connector 2.1.0

Docs
Support
logintc-user

GENERAL

Configurations
Logs

APPLIANCE

Status
Settings
Upgrade

New Configuration / First Factor

Step 2 of 4

Cancel

First Factor

☒ LDAP
☐ Active Directory
☐ RADIUS
☐ None

Select the first way users will authenticate prior to LoginTC.

Connect to an existing LDAP server for username / password verification.

LDAP Server Details

The LDAP host and port information.

Host

Host name or IP address of the LDAP server. Examples: ldap.example.com or 192.168.1.42

Port (optional)

389

Port if LDAP server uses non-standard port.

Bind Details

☒ Bind with credentials
☐ Anonymous

Active Directory / LDAP Option

Select **Active Directory** if you have an AD Server. For all other LDAP-speaking directory services, such as OpenDJ or OpenLDAP, select **LDAP**:

LoginTC RADIUS Connector 2.1.0

Docs
Support
logintc-user

GENERAL

Configurations
Logs

APPLIANCE

Status
Settings
Upgrade

New Configuration / First Factor

Step 2 of 4

Cancel

First Factor

☐ LDAP
☒ Active Directory
☐ RADIUS
☐ None

Select the first way users will authenticate prior to LoginTC.

Connect to an existing Active Directory server for username / password verification.

AD Server Details

The Active Directory host and port information.

Host

Host name or IP address of the LDAP server. Examples: ad.example.com or 192.168.1.42

Port (optional)

389

Port if Active Directory server uses non-standard port.

Bind Details

☒ Bind with credentials
☐ Anonymous

Configuration values:

Property	Explanation	Examples
host	Host or IP address of the LDAP server	ldap.example.com or 192.168.1.42
port (optional)	Port if LDAP server uses non-standard (i.e., 389 / 636)	4000
bind_dn	DN of a user with read access to the directory	cn=admin,dc=example,dc=com
bind_password	The password for the above bind_dn account	password
base_dn	The top-level DN that you wish to query from	dc=example,dc=com

7/25

Property	Explanation	Examples
<code>attr_username</code>	The attribute containing the user's username	<code>sAMAccountName</code> or <code>uid</code>
<code>attr_name</code>	The attribute containing the user's real name	<code>displayName</code> or <code>cn</code>
<code>attr_email</code>	The attribute containing the user's email address	<code>mail</code> or <code>email</code>
Group Attribute (optional)	Specify an additional user group attribute to be returned the authenticating server.	<code>SSLVPN-Users</code>
RADIUS Group Attribute (optional)	Name of RADIUS attribute to send back	<code>Filter-Id</code>
LDAP Group / AD Group (optional)	A comma delimited list of the names of possible LDAP groups to be sent back to the authenticating server. The user must be a member of a group for the attribute to be sent back. Groups membership is checked in priority order, if the user is a member of multiple groups the first group matched is returned.	<code>SSLVPN-Users</code> or <code>Administrators,Sales,Engineers</code>
encryption (optional)	Encryption mechanism	<code>ssl</code> or <code>startTLS</code>
cacert (optional)	CA certificate file (PEM format)	<code>/opt/logintc/cacert.pem</code>

Group Attribute and Access Control

LDAP Group / AD Group : The name of a group in the LDAP Directory that all authenticating users belong to.

Click **Test** to validate the values and then click **Next**.

Existing RADIUS Server Option

If you want to use your existing RADIUS server, select **RADIUS**:

LoginTC RADIUS Connector 2.1.0

[Docs](#)
[Support](#)
[loginc-user](#)

GENERAL

- Configurations
- Logs

APPLIANCE

- Status
- Settings
- Upgrade

New Configuration / First Factor

Step 2 of 4 Cancel

First Factor

☐ LDAP
 ☐ Active Directory
 ☒ RADIUS
 ☐ None

Select the first way users will authenticate prior to LoginTC.

Connect to an existing RADIUS server for username / password verification.

RADIUS Server Details

The RADIUS host and secret.

Host

Host name or IP address of the RADIUS server. Examples: ldap.example.com or 192.168.1.42

Port (optional)

Port if the RADIUS server uses non-standard port.

Secret

Configuration values:

Property	Explanation	Examples
host	Host or IP address of the RADIUS server	radius.example.com or 192.168.1.43
port (optional)	Port if the RADIUS server uses non-standard (i.e., 1812)	1812
secret	The secret shared between the RADIUS server and the LoginTC RADIUS Connector	testing123

RADIUS Vendor-Specific Attributes

Common Vendor-Specific Attributes (VSAs) found in the FreeRADIUS dictionary files will be relayed.

Click **Test** to validate the values and then click **Next**.

Passthrough

Configure which users will be challenged with LoginTC. This allows you to control how LoginTC will be phased in for your users. This flexibility allows for seamless testing and roll out.

For example, with smaller or proof of concept deployments select the Static List option. Users on the static list will be challenged with LoginTC, while those not on the list will only be challenged with the configured First Authentication Factor. That means you will be able to test LoginTC without affecting existing users accessing your VPN.

For larger deployments you can elect to use the Active Directory or LDAP Group option. Only users part of a particular LDAP or Active Directory Group will be challenged with LoginTC. As your users are migrating to LoginTC your LDAP and Active Directory group policy will ensure that they will be challenged with LoginTC. Users not part of the group will only be challenged with the configured First Authentication Factor.

No Passthrough (default)

Select this option if you wish every user to be challenged with LoginTC.

The screenshot shows the LoginTC web interface. The top navigation bar includes the LoginTC logo, the version 'LoginTC RADIUS Connector 2.1.0', and links for 'Docs', 'Support', and a user profile 'logintc-user'. A left sidebar contains a 'GENERAL' section with 'Configurations' and 'Logs', and an 'APPLIANCE' section with 'Status', 'Settings', and 'Upgrade'. The main content area is titled 'New Configuration / Passthrough' and indicates 'Step 3 of 4'. Under the 'Passthrough' heading, four radio buttons are shown: 'No Passthrough' (selected), 'Static List', 'LDAP Group', and 'Active Directory Group'. A description states: 'Configure list of users which will not be challenged by LoginTC. All authentications will be challenged with LoginTC. This can be configured at anytime.' A green 'Next' button is located at the bottom of the configuration area.

Static List

Select this option if you wish to have a static list of users that will be challenged with LoginTC. Good for small number of users.

This screenshot shows the 'Static List' configuration in the LoginTC interface. The 'Static List' radio button is selected. The description reads: 'Store static list of users that will be challenged with LoginTC. Good for small number of users.' Below this, a section titled 'Static List' explains: 'Only users in this list will be challenged with LoginTC. All other users will be challenged with configured first factor only.' To the right, under the heading 'LoginTC challenge users', there is a large, empty text area for entering the list of usernames.

LoginTC challenge users: a new line separated list of usernames. For example:

```
jane.doe
jane.smith
john.doe
john.smith
```

Active Directory / LDAP Group

Select this option if you wish to have only users part of a particular Active Directory or LDAP group to be challenged with LoginTC. Good for medium and large number of users.

Configuration values:

Property	Explanation	Examples
<code>logintc_challenge_auth_groups</code>	Comma separated list of groups for which users will be challenged with LoginTC	<code>SSLVPN-Users</code> or <code>two-factor-users</code>
<code>host</code>	Host or IP address of the LDAP server	<code>ldap.example.com</code> or <code>192.168.1.42</code>
<code>port</code> (optional)	Port if LDAP server uses non-standard (i.e., <code>389</code> / <code>636</code>)	<code>4000</code>
<code>bind_dn</code>	DN of a user with read access to the directory	<code>cn=admin,dc=example,dc=com</code>
<code>bind_password</code>	The password for the above <code>bind_dn</code> account	<code>password</code>
<code>base_dn</code>	The top-level DN that you wish to query from	<code>dc=example,dc=com</code>
<code>attr_username</code>	The attribute containing the user's username	<code>sAMAccountName</code> or <code>uid</code>
<code>attr_name</code>	The attribute containing the user's real name	<code>displayName</code> or <code>cn</code>
<code>attr_email</code>	The attribute containing the user's email address	<code>mail</code> or <code>email</code>
<code>encryption</code> (optional)	Encryption mechanism	<code>ssl</code> or <code>startTLS</code>
<code>cacert</code> (optional)	CA certificate file (PEM format)	<code>/opt/logintc/cacert.pem</code>

Configuration Simplified

If Active Directory / LDAP Option was selected in First Authentication Factor the non-sensitive values will be pre-populated to avoid retyping and potential typos.

Click **Test** to validate the values and then click **Next**.

Client and Encryption

Configure RADIUS client (e.g. your RADIUS-speaking VPN):

GENERAL

Configurations

Logs

APPLIANCE

Status

Settings

Upgrade

New Configuration / Client and Encryption Step 4 of 4 Cancel

Client Settings

Settings for your RADIUS client (e.g. a RADIUS-speaking VPN) to connect to the LoginTC RADIUS Connector.

Name

A unique identifier of your RADIUS client. Use only alphanumeric characters and hyphens. This will also be used for the name of the configuration file. Example: corp-vpn-1 will be saved on disk as corp-vpn-1.cfg.

IP Address

The IP address of your RADIUS client.

Secret

The secret shared between your RADIUS client and the LoginTC RADIUS Connector.

Encryption

☒ **Encrypt all passwords and API keys**

It is strongly recommended to encrypt all sensitive fields.

Client configuration values:

Property	Explanation	Examples
name	A unique identifier of your RADIUS client	CorporateVPN
ip	The IP address of your RADIUS client (e.g. your RADIUS-speaking VPN)	192.168.1.44
secret	The secret shared between the LoginTC RADIUS Connector and its client	bigsecret

Under Authentication Mode select **Challenge**

GENERAL

Configurations

Logs

APPLIANCE

Status

Settings

Configurations / New Configuration / Client and Encryption Step 4 of 4 Cancel

Authentication Mode

How the LoginTC RADIUS Connector will perform the second factor.

☐ Direct ☐ Iframe ☒ Challenge

The user will be prompted on how they wish to proceed with second-factor authentication (e.g. LoginTC Push, OTP, bypass code). Your RADIUS client must support RADIUS challenges to use this. Challenging the user will often result in a better user experience.

Challenge Message

Press 1 to authenticate with the LoginTC app or enter an OTP or bypass code.

The message that will appear to the user for the challenge. Note that the user must enter 1 for a LoginTC Push, or must enter an OTP or bypass code.

Encryption

☒ **Encrypt all passwords and API keys**


It is strongly recommended to encrypt all sensitive fields.

The user will be prompted on how they wish to proceed with second-factor authentication (e.g. LoginTC Push, OTP, bypass code). Your RADIUS client must support RADIUS challenges to use this. Challenging the user will often result in a better user experience. See [User Experience](#) for more information.

Data Encryption

It is strongly recommended to enable encryption of all sensitive fields for both PCI compliance and as a general best practice.


Click **Test** to validate the values and then click **Save**.




Testing (Connector)

When you are ready to test your configuration, create a LoginTC user (if you haven't already done so). The username should match your existing user. Provision a token by following the steps:


When you have loaded a token for your new user and domain, navigate to your appliance **web interface** URL:



Click **Test Configuration**:




Enter a valid username and password; if there is no password leave it blank. A simulated authentication request will be sent to the mobile or desktop device with the user token loaded. Approve the request to continue:




Congratulations! Your appliance can successfully broker first and second factor authentication. The only remaining step is to configure your RADIUS device!

If there was an error during testing, the following will appear:




In this case, click **See logs** and then click the `/var/log/logintc/authenticate.log` tab to view the log file and troubleshoot:



SonicWALL SRA - Quick Config Guide

Once you are satisfied with your setup, configure your SonicWALL SRA to use the LoginTC RADIUS Connector.


For your reference, the appliance **web interface Settings** page displays the appliance IP address and RADIUS ports:



The following are quick steps to get VPN access protected with LoginTC. The instructions can be used for existing setups as well. Although these were performed on SonicWALL SRA SRA, the same instructions will work on other devices as well.

Configure SonicWALL SRA

1. Log in to your SonicWALL SRA (Web UI)



2. Click **Portals > Portals > Add Portal:**



User: admin Mode: Configuration

System
Network
Portals
Portals
Application Offloading
Domains
Custom Logos
Load Balancing
URL Based Aliasing
Services
NetExtender
End Point Control
Secure Virtual Assist

Portals > Portals

<input type="checkbox"/>	Portal Name ▼	Description	Virtual Host Settings	Configure
<input type="checkbox"/>	VirtualOffice	Secure Remote Access	N/A	

Add Portal ... Offload Web Application ... Delete Selected Portals

Status: Ready

3. Enter a **Portal Name** (for example: Web-Portal):



User: admin Mode: Configuration

System
Network
Portals
Portals
Application Offloading
Domains
Custom Logos
Load Balancing
URL Based Aliasing
Services
NetExtender
End Point Control
Secure Virtual Assist
Secure Virtual Meeting
Web Application Firewall
Geo IP & Botnet Filter
High Availability
Users
Log
Virtual Office

Portals > Portals > Add Portal

Accept Cancel

General Login Schedule Home Page Virtual Assist Virtual Meeting Virtual Host Logo

Portal Settings

Portal Name: Web-Portal

Portal Site Title: Virtual Office

Portal Banner Title: Virtual Office

Login Message: <h1>Welcome to the Dell SonicWALL Virtual Office</h1><p>The Dell SonicWALL Virtual Office provides easy and secure remote access
to your

Portal URL: https://10.0.10.238/portal/Web-Portal

☒ Display custom login page

☒ Display login message on custom login page

☐ Hide Domain list on portal login page

☒ Enable HttpOnly for SRA cookies

☒ Enable HTTP meta tags for cache control (recommended)

☐ Enable ActiveX web cache cleaner

☒ Enforce login uniqueness


Enforcement method: Automatically logout existing session

☐ Enforce client source uniqueness

Small Logo:

NOTE: Save a copy of the **Portal URL** for future reference.

- Click the **Virtual Host** tab:
- Enter a **Virtual Host Domain Name** (for example: vpn.example.com)

 SonicWALL | Secure Remote Access Help | Logout

User: admin Mode: Configuration

Portals > Portals > Add Portal ?

General | Login Schedule | Home Page | Virtual Assist | Virtual Meeting | **Virtual Host** | Logo

Virtual Host Settings

Virtual Host Domain Name:

Virtual Host Alias (optional):

Virtual Host Interface: ?

Virtual Host IP Address:

Virtual Host IPv6 Address:

Note: Portals must have unique Virtual Host IP Addresses (if specified).

Virtual Host Certificate: ?

☐ Enable Virtual Host Domain SSO ?

Shared Domain Name: ?

Advanced SSL/TLS settings

Enforce Forward Secrecy: ?

Verify Backend SSL Server Certificate for Proxy connections: ?

☐ Force SSL/TLS version for Proxy connections ?

- Click **Accept** button

User: admin Mode: Configuration

Portals > Portals > Add Portal Accept Cancel ?

General Login Schedule Home Page Virtual Assist Virtual Meeting Virtual Host Logo

Virtual Host Settings

Virtual Host Domain Name:

Virtual Host Alias (optional):

Virtual Host Interface:

Virtual Host IP Address:

Virtual Host IPv6 Address:

Note: Portals must have unique Virtual Host IP Addresses (if specified).

Virtual Host Certificate:

☐ Enable Virtual Host Domain SSO ?

Shared Domain Name: ?

Advanced SSL/TLS settings

Enforce Forward Secrecy: ?

Verify Backend SSL Server Certificate for Proxy connections: ?

Status: Ready

7. Click **Portals > Domains > Add Domain**:

User: admin Mode: Configuration

Portals > Domains ?

Domain Name ▼	Authentication	Portal	Configure
LocalDomain	Local User Database	VirtualOffice	? ?

Add Domain ...

Status: Ready

8. Complete the required fields:



User: admin Mode: Configuration

Portals > Domains > Edit Domain 'LoginTC-RADIUS' Accept Cancel ?

General Test

Authentication type: Radius

Domain name: LoginTC-RADIUS

Authentication Protocol: PAP

Primary Radius server

Radius server address: 192.168.0.56

Radius server port: 1812

Secret password:

Radius Timeout (Seconds): 90

Max Retries: 1

Backup Radius server

Radius server address:

Radius server port: 1812

Secret password:

☐ Use Filter-ID For RADIUS Groups

Portal name: VirtualOffice

Status: Ready

Property	Explanation	Example
Domain name	The name of the SonicWALL SRA domain L	oginTC-RADIUS
Authentication Protocol	The type of RADIUS protocol to use. Must be PAP.	PAP
Radius server address	Address of LoginTC RADIUS Connector	10.0.10.130
Radius server port	RADIUS authentication port. Must be 1812.	1812
Secret password	The secret shared between the LoginTC RADIUS Connector and its client	bigsecret
Radius Timeout (Seconds)	Amount of time in seconds to wait. At least 90s.	90
Max Retries	Amount of times to retry authentication. Must be 1.	1

9. Click **Accept** button



User: admin Mode: Configuration

Portals > Domains > Edit Domain 'LoginTC-RADIUS' Accept Cancel ?

General Test

Authentication type: Radius

Domain name: LoginTC-RADIUS

Authentication Protocol: PAP

Primary Radius server

Radius server address: 192.168.0.56

Radius server port: 1812

Secret password:

Radius Timeout (Seconds): 90

Max Retries: 1

Backup Radius server

Radius server address:

Radius server port: 1812

Secret password:

☐ Use Filter-ID For RADIUS Groups


Portal name: VirtualOffice

Status: Ready

You are now ready to test your configuration.

Testing (SonicWALL SRA Configuration)

To test, navigate to your SonicWALL SRA clientless VPN portal (the **Portal URL** from Step 3 in [SonicWALL SRA - Quick Config Guide](#)) or use a SonicWALL SRA Mobile client and attempt access.


 SonicWALL | Virtual Office

Welcome to the Dell SonicWALL Virtual Office

The Dell SonicWALL Virtual Office provides easy and secure remote access to your corporate network from anywhere on the Internet.

Username:

Password:

Domain: 

SonicWALL SRA

Failover

SonicWALL devices have built-in settings that make it easy to configure a secondary RADIUS server to provide failover.

Edit the **Backup Radius server** portion of the SonicWALL SRA Radius domain to configure failover:



User: admin Mode: Configuration

System	Domain name: LoginTC-RADIUS
Network	Authentication Protocol: PAP
Portals	Primary Radius server
Portals	Radius server address: 192.168.0.56
Application Offloading	Radius server port: 1812
Domains	Secret password:
Custom Logos	Radius Timeout (Seconds): 90
Load Balancing	Max Retries: 1
URL Based Aliasing	Backup Radius server
Services	Radius server address: 192.168.0.57
NetExtender	Radius server port: 1812
End Point Control	Secret password:
Secure Virtual Assist	<input type="checkbox"/> Use Filter-ID For RADIUS Groups
Secure Virtual Meeting	Portal name: VirtualOffice
Web Application Firewall	Web-Portal
Geo IP & Botnet Filter	<input type="checkbox"/> Enable client certificate enforcement
High Availability	<input type="checkbox"/> Delete external user accounts on logout
Users	<input type="checkbox"/> Only allow users listed locally
Log	<input checked="" type="checkbox"/> Auto-assign groups at login
Virtual Office	

Status: Ready

Troubleshooting

No Network Connection

1. First ensure that your LoginTC RADIUS Connector is configured to have a virtual network adapter on `eth0`
2. Ensure that the virtual network adapter MAC address matches the one in the file `/etc/sysconfig/network-scripts/ifcfg-eth0`
3. Restart the networking service:

```
service network restart
```

4. If you notice the error that `eth0` is not enabled, then check driver messages for more information:

```
dmesg | grep eth
```


5. It's possible that the virtualization software renamed the network adapter to `eth1`. If this is the case, rename `/etc/sysconfig/network-scripts/ifcfg-eth0` to `ifcfg-eth1`.

```
mv /etc/sysconfig/network-scripts/ifcfg-eth0 /etc/sysconfig/network-scripts/ifcfg-eth1
```


Open the file and update the `DEVICE="eth0"` line to `DEVICE="eth1"`

Not Authenticating

If you are unable to authenticate, navigate to your appliance **web interface** URL and click **Status**:



Ensure that all the status checks pass. For additional troubleshooting, click **Logs**:



Unsuccessful authentication may be caused by premature [timeouts](#)

Authentication Timing Out

If authentication is failing, it is possible that the authentication requests are timing out too quickly. By default, LoginTC push requests will timeout after 90 seconds. Another timeout value is defined by the RADIUS server configuration. If it is set too low, it will cause requests to prematurely timeout.

Email Support

For any additional help please email support@cyphercor.com. Expect a speedy reply.